

## FreeNAS - Bug #41355

### Support CIDR subnets for allowed iSCSI initiators in new UI

08/13/2018 07:02 AM - KDragon Administrator

<b>Status:</b> Done	
<b>Priority:</b> No priority	
<b>Assignee:</b> Lola Yang	
<b>Category:</b> GUI (new)	
<b>Target version:</b> 11.2-BETA3	
<b>Seen in:</b> 11.2-BETA2	<b>Needs Merging:</b> No
<b>Severity:</b> New	<b>Needs Automation:</b> No
<b>Reason for Closing:</b>	<b>Support Suite Ticket:</b> n/a
<b>Reason for Blocked:</b>	<b>Hardware Configuration:</b>
<b>Needs QA:</b> No	<b>ChangeLog Required:</b> No
<b>Needs Doc:</b> No	
<b>Description</b> In the old UI you could enter allowed subnet in CIDR format one per line. The new UI does not allow this and there are no hints about using any delimiting characters. This does not allow for flexible and secure "masking" of initiators by subnet.	

#### History

##### #1 - 08/13/2018 07:27 AM - Dru Lavigne

- Assignee changed from Release Council to Erin Clark
- Target version changed from Backlog to 11.2-BETA3

##### #2 - 08/13/2018 01:44 PM - Erin Clark

- Assignee changed from Erin Clark to Lola Yang

##### #3 - 08/13/2018 04:20 PM - Lola Yang

- Status changed from Unscreened to In Progress

<https://github.com/freenas/webui/pull/1132>

This ticket need tooltip update. The authorized network field accepts multiple networks, and the delimiter is space. (e.g. 10.211.1.2/32 10.211.1.3/32)

##### #4 - 08/15/2018 01:10 PM - Erin Clark

- Status changed from In Progress to Ready for Testing

##### #5 - 08/15/2018 01:19 PM - Dru Lavigne

- Subject changed from iSCSI Initiator Allowed Subnets to Support CIDR subnets for allowed iSCSI initiators in new UI
- Needs Merging changed from Yes to No

##### #7 - 08/15/2018 01:20 PM - Dru Lavigne

- Subject changed from Support CIDR subnets for allowed iSCSI initiators in new UI to Support CIDR subnets for allowed iSCSI initiators in new UI

##### #8 - 08/27/2018 08:22 AM - Timothy Moore II

- Status changed from Ready for Testing to Passed Testing

- Needs QA changed from Yes to No

Testing with a FreeNAS system updated to FreeNAS-11.2-MASTER-201808270839:

Log in and go to Sharing -> iSCSI. Add a new Initiator and add multiple CIDR IP addresses separated by spaces in the Authorized Network field. Click SAVE. UI accepts these settings and displays them in the Initiators list.

**#9 - 08/27/2018 08:43 AM - Timothy Moore II**

PR to update help text for Authorized Network field: <https://github.com/freenas/webui/pull/1197>

Docs PRs: [angulargui branch] <https://github.com/freenas/freenas-docs/pull/321> [master branch] <https://github.com/freenas/freenas-docs/pull/322>

**#10 - 08/27/2018 08:58 AM - Timothy Moore II**

- Needs Doc changed from Yes to No

**#11 - 08/27/2018 10:44 AM - Dru Lavigne**

- Status changed from Passed Testing to Done